

## [External Browser Option](#)


The external browser option allows the user to process orders through the preferred internet browsing software.

### [VCA Tracer](#)

VCA Tracer has the option to use it's own internal browser or the users default browser.

To change the current selection go to the '[Settings](#)' button on the bottom of the screen. The '[Communication](#)' tab will be displayed. From the tabs at the top of the window select the 'Lab Set up' tab.

There are a number of options on this window. The option that needs to be selected is '[External Browser](#)'



The screenshot shows a settings window with the following elements: a checkbox for 'External Browser' which is currently unchecked, a checked checkbox for 'Show Shape on completion', and a text input field for 'Min. job length:'. At the bottom of the window are three buttons: 'Close', 'Settings', and 'View Web Site'.

If this option is ticked VCATracer will use the default internet browser (Chrome, Firefox, etc). If this is not ticked then the internal browser will be used.

Once the appropriate selection has been made. Restart VCATracer and continue with the processing of orders.


**Note:** This option will look noticeably different as it will be using a standard internet browser.

### [Raptor Order Grabber/Send RX to Supplier](#)

Raptor Order Grabber also has the option to use it's own internal browser or the users default browser.

To change the current selection go to the '[Configuration](#)' tab on the top of the screen.

There are a number of options on this window. Select a Lab from the left side of the window. Next



The screenshot shows a configuration window with a dropdown menu on the left showing 'Seiko' and 'Shamir'. Below the dropdown are three checkboxes: 'Automatic Update' (checked), 'External Browser' (unchecked), and 'Zip before sending' (unchecked). On the right side, there are buttons for 'Update', 'View Web Site', and 'View Mapping'. Below these buttons is a section for 'Traces' with a text input for 'Folder for traces:' and a checked checkbox for 'Use Tray number'. To the right of this is a text input for 'Trace file ext.' with '.OMA' entered. Below the 'Traces' section is a link for 'Labman Frame Shape Export' and two buttons: 'CSV Supplier Configuration' and 'Proxy Settings'.

select the required option of '[External Browser](#)' by placing or removing the tick.

**If this option is ticked Raptor will use the default internet browser (Chrome, Firefox, etc). If this is not ticked then the internal browser will be used. Once selected click on the [Update Button](#).**

The screenshot shows a configuration window with the following fields and options:

- Reference: [Text Input]
- Code Prefix: [Text Input]
- Web Service
- Service: <http://www3.solenzara.co.uk/cgi-bin/seiko/slwscgi.exe/soap>
- Labman Supplier Code: [Text Input]
- Use Ediconv
- Tracking
- Buttons: Update, View Web Site, View Mapping
- Traces section (highlighted in green):
  - Folder for traces: [Text Input]
  - Use Tray number
  - Trace file ext.: .OMA
- Labman Frame Shape Export: [Text Input]
- Buttons: CSV Supplier Configuration, Proxy Settings

**Once the appropriate selection has been made. Restart Raptor/Annapurna and continue with the processing of orders.**

**Note: This option will look noticeably different as it will be using a standard internet browser.**